VMS Workstation Software V4.3 Cover Letter

Order No.: AV-JK76J-TE

Workstations Engineering is happy to introduce V4.3 of VMS Workstation Software.

In this kit, you will find all software necessary to install VWS V4.3 on your workstation.

NOTE

This V4.3 kit is not limited to VWS. It includes components that will aid you in migrating from VWS to DECwindows.

- **VAXuisx Run-Time Library for VMS (NEW)**
- **UIS Source Code Annotator**
- **UIS to DDIF Converter**
- **DECwindows X11 Server**
- **Guide to Migrating VWS Applications to DECwindows**

VMS Workstation Software V4.3 incorporates both new and revised documentation.

New Manuals:

- VAXuisx Release Notes
- VAXuisx User's Guide
- UIS Source Code Annotator

Revised Manuals:

- VMS Workstation Software Read Me First, AV-GS96J-TE
- Installation Guide for VMS Workstation Software and Migration Tools, AA-HX11J-TE (This now includes installation procedures for all VWS and Migration products.)
- VMS Workstation Software Release Notes, AA-KP45F-TE

Before you attempt to install the VMS Workstation Software V4.3 kit, be sure to read the ''Read Me First'' pages included with your documentation and any relevant portions of the installation guide.

CONTENTS OF YOUR SOFTWARE KIT

Your VWS kit consists of one the following media:

- A set of 22 RX33 floppy disks
- A TK50 tape cartridge
- A 9 track magnetic tape

Copyright © 1990 Digital Equipment Corporation

PROGRAMMING NOTE:

In the VWS V4.1 release, all the DOP definitions in VWSSYSDEF were inadvertently changed to uppercase. This created an incompatibility for case-sensitive programming languages. The VWS development team apologizes for any inconvenience this might have caused you. The DOP definitions will remain uppercase for all future releases.

REMEMBER:

- To use VWS V4.3, you must have VMS V5.0 or above installed on your system.
- To use SIGHT, HCUIS or the VWS DEMO Kit, you must have VMS V5.0 or above installed on your system.
- To use the VAXuisx Run-Time Library, you must have VMS V5.3 or above installed on your system.
- To use the UIS to DDIF Converter and the UIS Source Code Annotator, you must have VMS V5.1 or above installed on your system.
- To use the DECwindows X11 server, you must have VMS V5.1 or VMS V5.2 installed on your system.
- To use some of the migraton tools in this kit, you must have DECwindows installed on your system. If you are running VMS V5.1, you must install DECwindows separately. If you are running VMS V5.2 or VMS V5.3, DECwindows can be installed as part of the normal VMS installation.

NOTE

After V4.3, RX33 distribution kits will no longer be available as distribution media for VWS or VWS Migration Tools.

CAUTION

If you receive the following warning message:

```
%SYSTEM-W-NOSUCHFILE, no such file
\VMI$ROOT:[SYSLIB]UISSHR.EXE
```

and it causes your installation to fail, please reinstall VWS after executing the following commands:

```
$ INSTALL REMOVE SYS$SHARE:UISSHR.EXE
$ INSTALL CREATE SYS$SHARE:UISSHR.EXE
```

The original installation failed because INSTALL could no longer locate the file associated with the installed file header information. The above commands will ensure that INSTALL can find the current copy of the file.